

# RHEL VLAN and Bonding Configuration

## Check list:

- Check whether the 8021q module has been loaded.
- `lsmod | grep 8021q`
- If the 8021q module is not loaded, run the following command to load it: `modprobe 8021q`

## Configuration

Add the following lines to `/etc/modprobe.conf` :

```
alias bond0 bonding
```

```
options bonding max_bonds=1
```

Edit `/etc/sysconfig/network-scripts/ifcfg-eth0` it should look something like this:

```
DEVICE=eth0
USERCTL=no
ONBOOT=yes
MASTER=bond0
SLAVE=yes
BOOTPROTO=none
HWADDR=
```

Edit `/etc/sysconfig/network-scripts/ifcfg-eth1` it should look something like this:

```
DEVICE=eth1
USERCTL=no
ONBOOT=yes
MASTER=bond0
SLAVE=yes
BOOTPROTO=none
HWADDR=
```

Now create the Bond0 interface:

NOTE: No IP address will be assigned to the bond0 device.

Create a new file `/etc/sysconfig/network-scripts/ifcfg-bond0` it should look like this:

```
DEVICE=bond0
BOOTPROTO=none
ONBOOT=yes
TYPE=Ethernet

BONDING_OPTS="mode=1 miimon=100"
```

NOTE: mode could be different, these are the mode options, but if Blade server is using Virtual Connect user should use mode=1.

mode=0 (balance-rr) Round-robin

mode=1 (active-backup) Active-backup

mode=2 (balance-xor) XOR

mode=3 (broadcast) Broadcast

mode=4 (802.3ad) IEEE 802.3ad Dynamic link aggregation

mode=5 (balance-tlb) Adaptive transmit load balancing

mode=6 (balance-alb) Adaptive load balancing

The first four modes are the most commonly used:

## VLAN tag setup

This will be a virtual interface with a VLAN tag of 48. User's VLAN set-up is most likely different so just replace 48 with the VLAN tag of user's network. i.e. bond1.50 would be the bonded interface for VLAN 50.

Create a new file `/etc/sysconfig/network-scripts/ifcfg-bond0. 48` it should look like this:

```
DEVICE=bond0. 48
ONBOOT=yes
TYPE=Ethernet
BOOTPROTO=static
VLAN=yes
NETMASK=255. 255. 255. 0
NETWORK=192. 168. 48. 0
IPADDR=192. 168. 48. 100
```

Ensure that the default gateway in this configuration is recorded in the `/etc/sysconfig/network` file otherwise it may not work properly. Once done, it should look something like:

```
NETWORKING=yes
HOSTNAME=
GATEWAY=192. 168. 48. 1
```

User has now setup bonding and VLAN tagging. User needs to restart networking to make the changes active.

```
service network restart
```

## Testing

Verify bonding interface is up and running

```
ifconfig -a
```

Verify configuration (RHEL 5 is using `sysfs` , so check out `/sys/class/net/` )

---

Revision #3

Created 5 April 2017 23:39:03 by Tingwai

Updated 17 April 2017 18:34:10 by Tingwai